

[Dec-2018300-075 Dumps PDF and VCE Free Download in Braindump2go[Q130-140

December/2018 Braindump2go 300-075 Exam Dumps with PDF and VCE New Updated Today! Following are some new 300-075 Real Exam Questions1.|2018 Latest 300-075 Exam Dumps (PDF & VCE) 459Q & As
Download:<https://www.braindump2go.com/300-075.html>2.|2018 Latest 300-075 Exam Questions & Answers Download:
<https://drive.google.com/drive/folders/0B75b5xYLjSSNRU9xWGk1cFJiaTg?usp=sharing>QUESTION 130Which functionality does ILS use to link all hub clusters in an ILS network?A. FullmeshB. AutomeshC. ILS updatesD. multicast**Answer: B**
QUESTION 131Which option is known as the location attribute that the global dialplan replication uses to advertise its dial plan information?A. location controllerB. route patternC. route stringD. URI**Answer: C**
QUESTION 132Refer to the exhibit. If an IP phone in San Jose roams to New York, which two IP phone settings will be modified by Device Mobility so that the phone can place and receive calls in New York? (Choose two.) A. The physical locations are not different, so the configuration of the phone is not modified.B. The physical locations are different, so the roaming-sensitive parameters of the roaming device pool are applied. C. The device mobility groups are the same, so the Device Mobility-related settings are applied in addition to the roaming-sensitive parameters.D. The Device Mobility information is associated with one or more device pools other than the home device pool of the phone, so one of the associated device pools is chosen based on a round-robin load-sharing algorithm.E. The Device Mobility information is associated with the home device pool of the phone, so the phone is considered to be in its home location. Device Mobility will reconfigure the roaming- sensitive settings of the phone.**Answer: BC**
QUESTION 133What happens when a user logs in using the Cisco Extension Mobility Service on a device for which the user has no user device profile?A. The Extension Mobility log in fails.B. The device takes on the default device profile for its type.C. The user can log in but does not have access to any features, soft key templates, or button templates.D. The device uses the first device profile assigned to the user in Cisco Unified Communications Manager.**Answer: B**
QUESTION 134Which three steps are required when configuring extension mobility in Cisco Unified Communications Manager? (Choose three.)A. Create the extension mobility IP Phone Service.B. Check the Home Cluster checkbox on the End User Configuration page.C. Check the Enable Extension Mobility checkbox on the Directory Number Configuration page.D. Unsubscribe all other services from the Cisco IP Phone.E. Create a user Device Profile.F. Subscribe the extension mobility IP Phone Service to the user Device Profile.**Answer: AEF**
QUESTION 135How many Cisco Unified Mobility destinations can be configured per user?A. 1B. 10C. 4D. 6**Answer: B**
QUESTION 136When configuring Cisco Unified Mobility, which parameter defines the access control for a call that reaches out to a remote destination?A. Calling Party Transformation Calling Search Space under Remote Destination Profile InformationB. User Local under Remote Destination Profile InformationC. Rerouting Calling Search Space under Remote Destination Profile InformationD. Rerouting Calling Search Space under Remote Destination informationE. Calling Search Space under Phone Configuration**Answer: C**
QUESTION 137Which two bandwidth management parameters are available during the configuration of Cisco Unified Communications Manager regions? (Choose two.)A. Default Audio Call RateB. Max Audio Bit RateC. Default Video Call RateD. Max Video Call Bit Rate (Includes Audio)E. Max Number of Video Sessions**Answer: BD**
QUESTION 138In Cisco Unified Communications Manager, where do you configure the default bit rate for audio and video devices?A. Enterprise ParametersB. Region under Region InformationC. Cisco CallManager service under Service Parameter ConfigurationD. Enterprise Phone Configuration**Answer: B**
QUESTION 139Which module is the minimum PVDM3 module needed to support video transcoding?A. PVDM3-32B. PVDM3-64C. PVDM3-128D. PVDM3-192**Answer: C**
QUESTION 140When implementing a Media Termination Point, what determines the number of sessions that is supported on each DSP?A. the codecs that are used in universal transcoding modeB. the size of the cluster that is being designedC. the number of full-duplex media streamsD. the Cisco Unified Communications Manager node setting**Answer: A**!!!RECOMMEND!!!1.|2018 Latest 300-075 Exam Dumps (PDF & VCE) 459Q & As Download:<https://www.braindump2go.com/300-075.html>2.|2018 Latest 300-075 Study Guide Video: YouTube Video: [YouTube.com/watch?v=y0hTJkN7kuI](https://www.youtube.com/watch?v=y0hTJkN7kuI)